



Template:EcosystemRelease

# Template:EcosystemRelease

Stable: 24.06.2020 - 09:02 / Revision: 15.06.2020 - 12:48

## Contents

1 Usage .....	2
2 Basic examples .....	3
3 More examples .....	3
4 Code .....	5

## 1 Usage

The `EcosystemRelease` template is used to indicate for which ecosystem release revision(s) of the flow associated with this wiki (e.g. v1.y.z, or v2.y.z, or...), **an article part (chapter, paragraph, table...) is valid**. Per default (i.e. if this template is not used), any part of an article is valid for all ecosystem release revisions for which the entire article is valid.

It outputs a "standardized" string that might be used to name an article part.

```
Usage: {{EcosystemRelease | revision=<revision> | range =<range> | revision2=<revision2>}}
```

Where:

- **<revision>** is the **mandatory** ecosystem release revision for which the article part is valid.
  - The possible values for this parameter are available in the `EcosystemRelease/Revision` template.
  - The optional **<range>** and **<revision2>** parameters allow to define a range of revisions.
- **<range>** is the **optional** range of the ecosystem release revisions for which the article part is valid. The possible values are:
  - **and before**: the article part is valid only for the revision(s) less than or equal to **<revision>**
  - **and after**: the article part is valid only for the revision(s) greater than or equal to **<revision>**
  - **to**: the article part is only valid from **<revision>** to **<revision2>**
- **<revision2>** is the **mandatory** ecosystem release upper revision for which the article part is valid, **when <range> is set to "to"**; in this case, **<revision>** becomes the lower revision for which the article part is valid.
  - This parameter is ignored if **<range>** is either not set, or set to another value than **"to"**.

If the mouse is left over a revision (or the  icon), a **popup window** shows, for that revision:

- the versions of the Linux kernel, U-Boot, TF-A and OP-TEE
- the version of the STM32Cube MPU Package
- the version of OpenEmbedded
- the version of Android

This information comes from the `EcosystemRelease/Components` template.



## 2 Basic examples

You type	You get
A specific revision (revision 2.0.0) <pre>{{EcosystemRelease   revision=2.0.0}}</pre>	ecosystem release v2.0.0 ⓘ
Revisions that are lower than or equal to a revision <pre>{{EcosystemRelease   revision=x.1.0   range=and before}}</pre>	ecosystem release vx.1.0 ⓘ
Revisions that are greater than or equal to a revision <pre>{{EcosystemRelease   revision=x.1.0   range=and after}}</pre>	ecosystem release vx.1.0 ⓘ
Range of revisions <pre>{{EcosystemRelease   revision=x.0.0   range=to   revision2=x.1.0}}</pre>	ecosystem release vx.0.0 ⓘ to vx.1.0 ⓘ

## 3 More examples

You type	You get
Revision x.1.0 <pre>{{EcosystemRelease   revision=x.1.0}}</pre>	ecosystem release vx.1.0 ⓘ



You type	You get
Revision x.0.0 <pre>{{EcosystemRelease   revision=x. 0.0}}</pre>	ecosystem release vx.0.0 ⓘ
Former revision that is part of a flow that is not the one associated with this wiki. <pre>{{EcosystemRelease   revision=0. y.0}}</pre>	ecosystem release v0.y.0 ⚠
Unspecified revision <pre>{{EcosystemRelease}}</pre>	ecosystem release unknown revision ⚠
Unknown revision <pre>{{EcosystemRelease   revision=10. 20.30}}</pre>	ecosystem release unknown revision 10.20.30 ⚠
Unspecified revision2 <pre>{{EcosystemRelease   revision=x. 1.0   range=to}}</pre>	ecosystem release vx.1.0 ⓘ to unknown revision ⚠
Unknown revision2 <pre>{{EcosystemRelease   revision=x. 1.0   range=to   revision2=10. 20.30}}</pre>	ecosystem release vx.1.0 ⓘ to unknown revision 10.20.30 ⚠
Former revision2 that is part of a flow that is not the one associated with this wiki. <pre>{{EcosystemRelease   revision=x. 0.0   range=to   revision2=0.y. 0}}</pre>	ecosystem release vx.0.0 ⓘ to v0.y.0 ⚠

You type	You get
<p>Ignored revision2</p> <pre> {{EcosystemRelease   revision=x.0.0   range=and after   revision2=x.1.0}}                     </pre>	<p>ecosystem release vx.0.0 ⓘ</p>
<p>Unknown range</p> <pre> {{EcosystemRelease   revision=x.1.0   range=error}}                     </pre>	<p>ecosystem release vx.1.0 ⓘ <b>unknown range error</b> ⚠</p>
<p>Check that there's no space before and after the text</p> <pre> BEFORE{{EcosystemRelease   revision=x.0.0}}AFTER&lt;br&gt; BEFORE{{EcosystemRelease   revision=x.1.0   range=and before}}AFTER&lt;br&gt; BEFORE{{EcosystemRelease   revision=x.1.0   range=and after}}AFTER&lt;br&gt; BEFORE{{EcosystemRelease   revision=x.0.0   range=to   revision2=x.1.0}}AFTER                     </pre>	<p>BEFOREecosystem release vx.0.0 ⓘ AFTER  BEFOREecosystem release vx.1.0 ⓘ AFTER  BEFOREecosystem release vx.1.0 ⓘ AFTER  BEFOREecosystem release vx.0.0 ⓘ to vx.1.0 ⓘ AFTER</p>

## 4 Code

ecosystem release **unknown revision** ⚠

Das U-Boot -- the Universal Boot Loader (see [U-Boot\\_overview](#))

Trusted Firmware for Arm Cortex-A

Open Portable Trusted Execution Environment

Microprocessor Unit